
## **Regional Settings**

The  ${\bf Regional\ Settings}$  information block contains the following fields:

Screenshot: Regional Settings block



Field	Description		
Default Currency	Specify <b>currency</b> that will be used as the default for the generation of routing and new entities creation (accounts, invoices, transactions, clients, resellers, etc.). However, this currency <b>won't</b> be used for reports.		
Default Language	Select your default language for the system. You can change it to your preferred language at any time.		
Timezone	Select your default timezone		
Year/Month Format	Specify how year/month will be displayed here		
	• %Y	Number of the <b>year</b> that consists of <b>4</b> numbers. Value example: <b>1999, 2005, 2010</b>	
	• %m	Month number. Allowed values: from 01 to 12	
Date Format	Specify date parameters here		
	• %d	Day of the month in numeric form. Allowed values: from 01 to 31	
	• %m	Month number. Allowed values: from 01 to 12	
	• %Y	Number of the <b>year</b> that consists of <b>4</b> numbers. Value example: <b>1999, 2005, 2010</b>	
Date and Time Format	Specify the date and time parameters here		
	• %d	Day of the month in numeric form. Allowed values: from 01 to 31	
	• %m	Month number. Allowed values: from 01 to 12	
	• %Y	Number of the <b>year</b> that consists of <b>4</b> numbers. Value example: <b>1999, 2005, 2010</b>	
	• %H	Hours in 24-hour format with leading zeroes. Allowed values: from 00 to 23	
	• %M	Minutes with leading zeroes. Allowed values: from 00 to 59	

	• %\$	Seconds with leading zeroes. Allowed values: from 00 to 59	
Date and Time w	Specify the date and time with timezone parameters here		
/TZ Format	• %d	Day of the month in numeric form. Allowed values: from 01 to 31	
	• %m	Month number. Allowed values: from 01 to 12	
	• %Y	Number of the <b>year</b> that consists of <b>4</b> numbers. Value example: <b>1999, 2005, 2010</b>	
	• %H	Hours in 24-hour format with leading zeroes. Allowed values: from 00 to 23	
	• %M	Minutes with leading zeroes. Allowed values: from 00 to 59	
	• %\$	Seconds with leading zeroes. Allowed values: from 00 to 59	
	• %z	Timezone settings	



## Attention

If you change the **Default Currency**, you need to restart the **Dynamic Routing Manager** in the **Task Scheduler** section for an immediate **Routing Analysis** functioning.